Local compiler switches

cmd	short	long	explanation
	$A	$ALIGN	Align Data.
A		$ASMMODE	Select assembler mode.
	$B	$BOOLEVAL	Use complete boolean evaluation.
Sa	$C	$ASSERTIONS	Enable assertion support.
		$CALLING	Set default calling convention
d		$DEFINE	Define a symbol.
		$ELSE	Switch conditional compilation.
		$ENDIF	End conditional compilation.
		$ERROR	Generate error message.
	$F		Use far or near functions.
		$FATAL	Generate fatal error message.
Sg		$GOTO	Support Goto and Label.
	$H	$LONGSTRINGS	Use AnsiStrings.
		$HINT	Generate hint message.
vh		$HINTS	Emit hints
		$IF	Start conditional compilation.
		$IFDEF	Start conditional compilation.
		$IFNDEF	Start conditional compilation.
		$IFOPT	Start conditional compilation.
		$INFO	Generate info message.
Si		$INLINE	Enable inline code support.
Ci	$I	$IOCHECKS	Include Input/Output checking.
	$I	$INCLUDE	Include file.
	$I	$INCLUDE	Include compiler info.
	$L	$LINK	Link object file.
		$LINKLIB	Link to a library.
	$M	$TYPEINFO	Generate Run-Time type information.
Sm		$MACRO	Enable macro support.
		$MAXFPUREGISTER	set maximum number of FPU registers
		$MESSAGE	Generate info message.
		$MMX	Enable Intel MMX support.
		$NOTE	Generate note message.
vn		$NOTES	Emit notes.
A		$OUTPUT_FORMAT	Select compiler output format.
	$P	$OPENSTRINGS	Use open strings.
		$PACKENUM	Specify minimum enumeration type size.
		$PACKRECORDS	Specify Alignment of record elements.
Co	$Q	$OVERFLOWCHECKS	Use overflow checking.
Cr	$R	$RANGECHECKS	Use range checking.
		$SATURATION	Enable saturation operations.
XX		$SMARTLINK	Use smartlinking.
St		$STATIC	Enable use of Static keyword.
		$STOP	Generate fatal error message.
	$T	$TYPEDADDRESS	Enable typed address operator.
u		$UNDEF	Undefine a symbol.
	$V	$VARSTRINGCHECKS	Use strict var-string checking.
		$WAIT	Wait for enter key press.
		$WARNING	Generate warning message.
		$WARNINGS	Emit warnings.
	$X	$EXTENDEDSYNTAX	Enable use of extended syntax.

Global compiler switches

cmd	short	long	explanation
		$APPID	Set application ID (PalmOS)
		$APPNAME	Set application name (PalmOS)
		$APPTYPE	Specify type of application (Windows only)
g	$D	$DEBUGINFO	Include debugging symbols.
		$DESCRIPTION	Not supported.
	$E		Enable emulation of coprocessor.
	$G		Generate 80286 code.
Fi		$INCLUDEPATH	Specify include file search path.
	$L	$LOCALSYMBOLS	Enable local symbol information.
Fl		$LIBRARYPATH	Specify library search path.
	$M	$MEMORY	Specify memory sizes.
M		$MODE	Specify compiler compatibility mode.
	$N		Enable numeric processing.
	$O		Enable overlay code generation.
Fo		$OBJECTPATH	Specify object file search path.
Ct	$S		Use stack checking
Fu		$UNITPATH	Specify unit file search path.
		$VERSION	Set DLL version (Windows)
	$W	$STACKFRAMES	Generate stackframes.
b	$Y	$REFERENCEINFO	Insert browser information.